STEELYSYSTEMS


FOR ELITE TRADERS WHO KNOW

SteelyBarExporter

Utility for NinjaTrader 8 · Chart bars to a CSV file

UTILITY · ANY INSTRUMENT · NO SIGNALS

What it does: Ever wanted to hand your candle data to your AI of choice to analyze the market? SteelyBarExporter saves your chart's bars to a CSV file you can use however you please: deep personal analysis, data-science work, or modeling with your favorite LLM.



NQ 1-minute in NinjaTrader 8 with the BarExporter HUD (top right), then the same bars' CSV rows, 09:31 to 09:40 ET; the 09:36 bar under the crosshair is highlighted. Shown for illustration only.

NEW TO DATA EXPORTS

Read the file at a glance

One header row, then one row per bar, oldest first. Times are bar closes: a 5-minute bar from 09:30 to 09:35 is stamped 09:35. Numbers always use a dot decimal.

bar_close_et	Close time in US Eastern time, converted from NinjaTrader's time zone with daylight saving handled.
bar_close_chart	Close time as NinjaTrader shows it on the chart.
trading_day	The session's trading day, from the chart's Trading Hours: on the default template, a bar closing 18:05 ET Monday belongs to Tuesday.
first_bar_of_session	1 on a session's first bar, otherwise 0.
open … volume	The bar's open, high, low and close, and the contracts traded in the bar.

Reading the HUD

EXPORTING…	History is being written: bars done out of bars loaded.
EXPORT COMPLETE	The file is on disk: bar count, first and last bar in ET, and the file name.
Live: +N bars	Bars added since the chart loaded, with the last bar's time, or the reason a bar could not be added.
NOT WRITTEN	No file was written, with the reason: no bars, bars not processed (press F5), or a write error.
Output window	[SteelyBarExporter v11.2] wrote N bars, first and last bar in ET, and the file path.

Drag the HUD to move it; double-click puts it back. Right-click the chart outside the HUD for the chart menu.

FOR DATA WORK

The rules, exactly

Load	Once the chart's history has loaded, every closed bar of its main data series is in the file. Rows go to a temporary .part file, which becomes the CSV at the end.
Append	In real time, with Append realtime bars on, each bar is added as it closes, only to a file this load wrote. If a bar is ever missed, appends stop, leaving no gap: press F5. Excel can block appends.
Reload	Every full chart load, including F5, writes a new file; delete old exports you no longer need. If the license check finished after loading started, the HUD says NOT WRITTEN: press F5.
File name	Instrument, bar size and the Eastern time the chart loaded, such as MNQ_12-26_1Minute_2026-11-13_112530.csv. With Timestamp in file name off: one file per instrument and bar size, replaced on each load.
Data	Gaps in NinjaTrader's stored data show up in the file; reload them under Tools › Historical Data. Times are to the second, so tick or volume bars can share one.

Get started in three steps

1. Find your license key and the download at whop.com/steelysystems (SteelyIndicators Download). Both are also in your purchase email.

2. In NinjaTrader 8: Tools › Import › NinjaScript Add-On, then select SteelyIndicators.zip (keep it zipped).

3. Open a chart, set **Days to load**, then right-click › Indicators › add **SteelyBarExporter** and paste your license key when asked.

Useful settings

Output folder (blank: Documents\NinjaTrader 8\SteelyExports) · **Append realtime bars** (on) · **Timestamp in file name** (on) · **Show HUD** (on) · **HUD position** (top right).

Get SteelyBarExporter → steelysys.com/steelybarexporter.html

info@steelysys.com

Educational and informational only; not a recommendation to buy or sell. Futures trading involves substantial risk of loss and is not suitable for every investor.
© 2026 Steely Systems LLC. NinjaTrader is a registered trademark of NinjaTrader, LLC; Steely Systems is not affiliated with NinjaTrader, LLC.